



Enhanced Operations Manager
Quick Start Installation Guide

Introduction

The following instructions are for a new installation of Novagem's Enhanced Operations Manager (EOM).

Once your installation is complete, you will need to set up a few simple parameters in order to send PDF documents, text messages and to monitor your iSeries and Windows Servers.

The full EOM User Manual is available on CD. You can also phone the Novagem Help Desk who will be more than happy to talk you through installation and operation of EOM. Contact the Help Desk on +44 (0)1992 505337.

Installing the Software

Depending whether you download the software from the web or have a CD, you have two options for installing the software EOM software on your iSeries :

OPTION 1 – DOWNLOAD FROM WEB

Download the software from the Support page on the Novagem website to your PC. Save the file as 'eomug'.

Sign-on with Security Officer access rights.

From the command line of your iSeries enter the following commands:

```
CRTLIB EOMUG  
press enter
```

```
CRTSAVF EOMUG/EOMUG  
press enter
```

From the PC used for downloading the software, binary FTP the save-file from the PC onto the iSeries into the EOMUG library. Then type:

```
RSTLIB SAVLIB(EOMUG)  
DEV(*SAVF) SAVF(EOMUG/EOMUG)  
MBROPT(*ALL) ALWOBJDIF(*ALL)  
press enter
```

```
EOMUG/EOMUG  
press enter
```

Press F10 to accept the license conditions.

OPTION 2 – INSTALL FROM CD

Sign-on with Security Officer access rights.

Place the EOM Version 5 CD into the iSeries CD-ROM drive.

From the command line of your iSeries enter the following commands (where nn is the CD-ROM drive number):

```
RSTLIB SAVLIB(EOMUG)  
DEV(OPTnn)  
press enter
```

```
EOMUG/EOMUG  
press enter
```

Press F10 to accept the license conditions.

Identify Resource Names

The install procedure checks whether the Novagem communication lines have been previously created and will prompt for the resource name(s) if they have not. If resource names are not known at this time then these entries can be left blank.

Use the iSeries WRKHDWRSC *CMN command to identify the resource name(s) you will use with the Land Line and or Cellular Connection Kit (CCK) modems that will be used to send SMS Text and Pager Messages.

If and when prompted enter the iSeries communication line resource name(s) if known and press enter

Modem Resource e.g.CMN01 . . .	_____	Character value
CCK Resource e.g. CMN01 . . .	_____	Character value
Is Modem an IBM 7852-400? . . .	'N'	Y, N

Specifying a "Y" in the above "Is Modem an IBM 7852-400?" field will tell EOM that the IBM Modem is set in Synchronous mode. (You can check this by referring to Page 53 in the User Guide).

Installation Complete

Once the software installation is complete you are now moments away from empowering your iSeries Community.

Refer to the Quick Start section in the User Guide on the CD or contact the Novagem help line on +44 (0)1992 505337 for technical and operational advice and information.